

KENTUCKY TRANSPORTATION CABINET

Kentucky TRNS*PORT Information Series

SiteManager Materials Module

LIMS Test Assignment Information Window

Navigation

System Admin\ Test Assignment Information Window

Test Assignment Information Window Description

To define the default test settings for a sample, use the Test Assignment function. The test assignment criteria consist of the following key information:

- n Material
- n Sample Type
- n Lab Unit

After making selections in the Test Assignment Criteria area, LIMS displays tests that meet specified criteria but do not have any assigned defaults in the Available Tests pane. LIMS also displays the tests that meet the specified criteria and do have assigned default tests in the Default Tests pane.

Note: LIMS selects the Default Test Ind check box by default. Selecting the Required Assign check box automatically selects the Default Test Ind check box (if it had been cleared). To indicate a test for the specific combination of keys is to be auto finalized, select the Autofinal Ind check box.

To add or remove default test settings, select the test and click the ADD DEFAULT TESTS or the REMOVE DEFAULT TESTS buttons. LIMS moves the selected test to or from the Available Tests pane and the Default Tests pane.

Procedure

Central Office Section Supervisor will define initial default tests. Once input by spreadsheet, System Administrator will maintain each assignment.

Field Table

Field Name	KYTC Population Policy & Procedure
Material Code	Identifies the material.
Material Name	Description of material.

KENTUCKY TRANSPORTATION CABINET

Kentucky TRNS*PORT Information Series

SiteManager Materials Module

Field Name	KYTC Population Policy & Procedure
Sample Type	Identifies the sample type. (U: SMPLTYPE).
Description	Identifies the sample type description.(U: SMPLTYPE).
Lab ID	Lab unit where the test is to be performed.
Lab Name	Identifies the name of the lab.
Test Method (Available Tests pane)	Identifies the test method for all material tests for the selected material and lab not yet assigned to the test assignment criteria.
Test Description (Available Tests pane)	Identifies the description of the test.
Test Method (Default Tests pane)	Identifies the test method for all material tests assigned to the test assignment criteria.
Test Description (Default Tests pane)	Identifies the description of the test.
Start Status	Identifies the initial test status for the test. Default value is set to the LIMS Default Test Status system operational parameter value.
Required Assign	Indicates whether the test is required for the selected test assignment criteria.
Autofinal Ind	<p>Indicates whether the test is a candidate for the LIMS auto finalization process for the selected test assignment criteria.</p> <p>Note: The auto finalization process will work only if the Autofinal Ind check box has been selected for all of the sample's tests.</p> <p>Visual Certifications will be marked as autofinalized.</p>
Default Test Ind	Indicates whether the test is a default test for the selected test assignment criteria.

KENTUCKY TRANSPORTATION CABINET

Kentucky TRNS*PORT Information Series

SiteManager Materials Module